



What to do if your Digitiser buttons do not work

(Especially if you use Tabletworks driver version 10 or greater)

The generic mapping of the puck buttons is not working, so you will need to force a button mapping. To do this you need to edit the parameters in the registry.

'Start | Run'
type in Regedit

On the left hand side of the double window pane, navigate to :
MyComputer\HKEY_CURRENT_USER\Software\AeiSoftware\Irricad\AppSettings\Tablet
(please note that these settings will not be there until you have gone into IRRICAD and exited out of IRRICAD the first time.)

Change the 'Use Driver Map' to equal 0
(Note if it is set to 1 then the digitiser will attempt to use the button map from the digitiser driver)

Under
MyComputer\HKEY_CURRENT_USER\Software\AeiSoftware\Irricad\AppSettings\NumButtons
This number should equal the number of buttons on your puck or stylus. If not, please change it.

Then there should be Button0, Button1, Button2 etc up to the number of buttons on your puck minus 1.
For the button that you wish to do the following action, put the corresponding numbers in.

Left Click – 1
Right Click – 4
Middle Click – 7
Escape – 15

When IRRICAD starts up, it will read the numbers and map the appropriate actions to the appropriate buttons.

IMPORTANT:
These mappings only apply in tablet mode. This can cause some issues. In order to avoid this, you must also enter the same mappings in the TabletWorks program.
'Start | Programs | TabletWorks'.

If you have any further problems, please contact your nearest IRRICAD support.